

eQart®

BY



eQart software release 2.3.4

Firmware updates

- User configured data like Main Color, Station Color and eQart size will be preserved on the cart, even after an update or change of tablet.
- New in-place rotation algorithm, utilizing cameras to better align with lines in missions.
- Improved RFID diagnostics. Minimizing false error detection.
- For in-place rotation, the corner LEDs will slash in light blue to indicate an autonomous operation.

Application updates

- When editing RFID tag number, station name is shown besides the tag to ease understanding.
- Fixed "Stop none localized" display issue.
- Option for CW/CCW preselected in mission according to map selected direction. This can however be overridden by changing for individual missions.
- Status 'ready to run' is no longer displayed if tablet is not connected to cart.
- Improved communication protocol to speed up application and cart commands.
- Fixed diagnose logging not being disabled if unselected in settings.
- New merge feature in the mission planner, allowing of merging two process flows.